

A-AUTO 50
License Activation Guide

Contents

1	License activation process.....	1
1.1	Get activation key and license key file	1
1.2	Register the license key file.....	2
1.2.1	Registration process for Basic License	2
1.2.2	Registration process for Remote License (Windows).....	3
1.2.3	Registration process for Remote License (Linux).....	4
1.3	Register the activation key (For Basic License only).....	5

1 License activation process

1.1 Get activation key and license key file

You can get these keys from email which delivered as a result of license issuance.



- ✓ If you didn't license issuance yet, please do it from "License Issuance" on left menu of A-AUTO 50 Website (<https://a-auto50.unirita.co.jp/en/>).

(1) Activation key (For Basic License only)

Activation key is the text string to activate A-AUTO Web Server.
It's written on body of the email.

(2) License key file

License key file is the file to activate A-AUTO Monitor.
It's attached to email.



1.2 Register the license key file


1.2.1 Registration process for Basic License

(1) Launch A-AUTO License Management Tool as bellow.


Start menu > All Programs > BSP > A-AUTO for Windows > License Registration



(2) Click "Add License", and select the license key file.



(3) Click "Yes" on confirmation dialog.




1.2.2 Registration process for Remote License (Windows)

(1) Launch A-AUTO License Management Tool as bellow.


Start menu > All Programs > BSP > A-REMOTE 50 > License Registration



(2) Click "Add License", and select the license key file.



(3) Click "Yes" on confirmation dialog.



1.2.3 Registration process for Remote License (Linux)

(1) Put the license key file on the computer which Remote License is installed.

- If you send the license key file with FTP, SCP, or the like, please set the transfer mode to "binary". Otherwise, A-AUTO 50 can't import the license key file.

(2) Stop "aremote50" service. (Root privilege is required)

```
# service aremote50 stop
```

(3) Backup "/opt/auto50/files/BSPLIC.KEY".

```
# mv /opt/auto50/files/BSPLIC.KEY /opt/auto50/files/BSPLIC.KEY_BK
```

(4) Move the license key file to "/opt/auto50/files" directory.


```
# ls
BSPLIC.KEY
# mv ./BSPLIC.KEY /opt/auto50/files
# ls /opt/auto50/files
aux_msgtbl BSPLIC.KEY BSPLIC.KEY_BK joblibdef LOG
```

(5) Launch "aremote50" service.


```
# service aremote50 start
```

1.3 Register the activation key (For Basic License only)

- (1) Launch A-AUTO Web Client, and click "Register the activationkey" at login page.
(Login page automatically opens when A-AUTO Web Client is launched.)



(2) Input the activation key, and click "Register".



(3) Check if the registration succeeded.

If you want to access the login page immediately, close A-AUTO Web Client and launch it again.

